



PADEL SENSITIVITY SETTING

xplova

2022/03/16

STEP 1 – Install the APP

1. Please install
“Xplova eBike Assistant” APP.



iOS



Android



STEP 2 – Power on



1. Turn on the display, the bike serial number (5-digital) is in the first screen. This serial number is used for Bluetooth connection.

For example : The serial number of this bike is 21796.





STEP 3 – Connect

1. Turn on the Bluetooth and connect the bike in the App.
2. Select the bike serial number.
(see previous step)



STEP 4 – Bike setting



1. Follow the steps to enter “Bike Setting”.



STEP 5 – Pedal sensitivity setting(Engine Type)


1. Adjust the “Engine Type” to set the pedal sensitivity.

Remark: If the acceleration is too powerful, please swift to left "Low sensitive".
If the acceleration is less powerful, please swift to right "High sensitive".



STEP 6 – Save changes

1. Please return to information page for saving changes.



STEP 7 – Riding test

1. Start riding test. If the acceleration is not as expected, follow the previous steps to re-adjust the pedal sensitivity.